



Little Sound Dj v8.3.1

Operating Manual

Little Sound Dj v8.3.1

Copyright © Johan Kotlinski ¹

March 15, 2020

¹With contributions from Aaron U. Thanks!

Contents

1	Introduction	7
1.1	Hi!	7
1.2	Important Notice	7
1.3	Game Boy Sound	8
1.4	Key Presses	8
1.5	Navigating the Program	9
1.6	Making Your First Sounds	10
1.7	Initial Troubleshooting	11
1.8	Hexadecimal Number System	12
2	The Screens	13
2.1	Screen Map	13
2.2	Moving between Screens	13
2.3	Starting and Stopping	14
2.4	Song Screen	14
2.5	Chain Screen	15
2.6	Phrase Screen	16
2.7	Instrument Screen	17
2.7.1	General Instrument Parameters	18
2.7.2	Pulse Instrument Parameters	19
2.7.3	Wave Instrument Parameters	20
2.7.4	Kit Instrument Parameters	21
2.7.5	Noise Instrument Parameters	22
2.7.6	Speech Instrument Parameters	23
2.8	Table Screen	23
2.8.1	Envelope Example	24
2.8.2	Arpeggio Example	24
2.9	Groove Screen	25
2.10	Synth Screen	26
2.10.1	Fixed Synth Settings	27
2.10.2	Variable Synth Settings	27

2.11	Wave Screen	30
2.12	Project Screen	30
2.12.1	Total Memory Reset	32
2.13	File Screen	32
2.13.1	Song List	33
2.14	Border Information	33
3	Advanced Techniques	35
3.1	Copy and Paste	35
3.2	Cloning	35
3.2.1	Deep vs. Slim-Cloning	36
3.3	The Importance of Backups	36
3.4	Muting, Soloing and Panning	36
3.5	Live Mode	37
3.5.1	Chain Loops	37
3.6	Synthetic Drum Instruments	38
3.6.1	Pulse Bass Drum	38
3.6.2	Snare Drum	38
3.6.3	Hi-Hats and Cymbals	38
3.6.4	Taking Advantage of Tables	38
3.6.5	Wave Bass Drum	38
4	Overview of Key Presses	43
5	Commands	47
5.1	A: Table Start/Stop	47
5.2	B: MayBe	47
5.2.1	In Phrases (MayBe Play Note)	47
5.2.2	In Tables (MayBe Hop)	48
5.3	C: Chord	48
5.3.1	For Pulse and Wave Instruments:	48
5.3.2	For Noise Instruments:	48
5.4	D: Delay	49
5.5	E: Amplitude Envelope	49
5.5.1	For Pulse and Noise Instruments	49
5.5.2	For Wave Instruments	49
5.6	F: Wave Frame/Finetune	49
5.6.1	For Pulse Instruments:	49
5.6.2	For Kit Instruments:	49
5.6.3	For Wave Instruments:	49
5.7	G: Groove Select	50

5.8	H: Hop	50
5.8.1	H in Phrases	50
5.8.2	H in Tables	51
5.9	K: Kill Note	51
5.10	L: Slide	51
5.10.1	L in Tables	52
5.11	M: Master Volume	52
5.12	O: Set Output	53
5.13	P: Pitch Bend	53
5.13.1	For Pulse, Wave and Kit Instruments:	53
5.13.2	For Noise Instruments:	53
5.14	R: Retrigger/Resync	53
5.15	S: Sweep/Shape	54
5.15.1	Pulse Instruments	54
5.15.2	Kit Instruments	54
5.15.3	Noise Instruments	54
5.16	T: Tempo	54
5.17	V: Vibrato	55
5.18	W: Wave	55
5.18.1	For Pulse Instruments:	55
5.18.2	For Wave Instruments:	55
5.19	Z: Randomize	55
6	Synchronization	57
6.1	Game Boy to Game Boy Sync	57
6.1.1	Activating LSDj Sync	57
6.1.2	Song Play	57
6.1.3	Live Play	58
6.1.4	Clipboard Transfer	58
6.1.5	Switching Lead while Playing	58
6.2	MIDI Sync	58
6.3	Analog In	59
6.4	Analog Out	59
6.5	Troubleshooting Cables	60
6.6	Keyboard Control	60
6.6.1	Keyboard Note Layout	60
7	Speech Programming	63
7.1	Introduction	63
7.2	Allophones	64
7.2.1	Short vowels	64

7.2.2	Long vowels	65
7.2.3	R-colored vowels	65
7.2.4	Resonants	65
7.2.5	Voiced fricatives	66
7.2.6	Voiceless fricatives	66
7.2.7	Voiced stops	66
7.2.8	Voiceless stops	67
7.2.9	Affricates	67
7.2.10	Nasal	67
8	The Sample Kits	69
A	SRAM Memory Map	75
A.1	Bank 0	75
A.2	Bank 1	75
A.3	Bank 2	77
A.4	Bank 3	77

Chapter 1

Introduction

1.1 Hi!

First of all, thanks for trying out Little Sound Dj!

A lot of effort has been put into making this program as powerful and fast-worked as possible. If you don't have previous experience from similar "tracker"-like music editors, the amount of new concepts may seem a bit overwhelming at first. Please, try not to stress about it. Learn step by step, keep it fun and progress at your own pace. Within days, you should know enough about the program to make your own first songs.

This manual is mostly written as an absolute beginners guide, but also as a reference that covers everything in the program. However, there still is a lot of information that would not fit into a manual like this. I highly recommend checking out the user-maintained Wiki site at <http://wiki.littlesounddj.com> - it contains material like tutorials, tips and tricks, and hardware related DIY projects. Also, the Facebook group at <https://www.facebook.com/groups/LittleSoundDJ/> is useful for getting in touch with other users. If you have questions, ideas or bug reports, please e-mail info@littlesounddj.com.

Happy tracking!

/Johan

1.2 Important Notice

Turning off the Game Boy while playing may cause your songs to be lost, so please avoid that. Also, it is best to avoid using the program when batteries are low enough to risk that the Game Boy shuts down itself. Low battery

level is indicated by the red light on your Game Boy becoming faint, or the screen becoming dim.

1.3 Game Boy Sound

The Game Boy sound chip has four channels, each with 4-bit resolution.

Pulse Channel 1 Square wave with envelope and sweep functions.

Pulse Channel 2 Square wave with envelope function.

Wave Channel Soft synthesizer, sample playback and speech synthesis.

Noise Channel Noise with envelope and shape functions.

1.4 Key Presses

In this documentation, key presses are marked up in this fashion:

A A button

B B button

START start button

SELECT select button

CURSOR any direction of the plus-shaped D-pad

LEFT D-pad left

RIGHT D-pad right

UP D-pad up

DOWN D-pad down

LEFT/RIGHT D-pad left or right

UP/DOWN D-pad up or down

SELECT+A pressing A while holding SELECT

SELECT+(B,B) pressing B twice, while holding SELECT

1.5 Navigating the Program

When starting LSDj, you will see the screen in figure 1.1.




Figure 1.1: Song Screen

The SONG title in the top left tells that this is the song screen, the place to arrange songs. The four columns with dashes each represent a Game Boy sound channel. There are two pulse wave channels, one custom wave channel (which uses sampled drum kits or soft-synthesized wave forms), and one noise channel. You can move between the channels using the D-pad.



Figure 1.2: Screen Map

Little Sound Dj has nine screens, laid out on a 5×2 map displayed in the bottom right of the screen (figure 1.2). You can navigate between the different screens by holding SELECT and pressing the D-pad.

The most useful screens are placed in the bottom row, ordered by level of detail. The song, chain and phrase screens are used for sequencing, and work together in a tree-structure fashion. The song contains chains, each chain contains phrases, and each phrase contains notes. They are followed by the instrument and table screens, which are used to create sounds.

1.6 Making Your First Sounds

Navigate to the song screen, and move the cursor to the PU1 column. Tap the A button, and a new chain "00" will appear. Edit the chain by pressing SELECT+RIGHT to enter the chain screen. There, tap A to insert a new phrase, then press SELECT+RIGHT to go to the phrase screen.




Figure 1.3: Phrase Screen

In the phrase screen, you can enter notes to be played back. Move the cursor to the note column and press A to enter a note. The text C-2 will appear: C being the note, and 2 the octave. Press START to play the phrase. Notice how the phrase is played back from top to bottom. You can change the note by holding A and pressing the D-pad. A+LEFT/RIGHT changes the note, and A+UP/DOWN changes octave.

Now, try to move the cursor and insert notes on other steps. To delete a note, press A while holding B. When you have finished listening, press START again to stop the phrase.

The clean pulse sound might get dull after while. Let's move on to the instrument screen by pressing SELECT+RIGHT.

In the instrument screen, we can make the sound a little bit more interesting. Try changing the ADSR and WAVE fields by moving the cursor there and pressing A+LEFT/RIGHT. As an example, setting the ADSR setting to A3 should make the sound more bouncy. Press START again to hear the changes as you make them!

The TYPE field sets the instrument type. Instrument types are specific for channels – PULSE instruments should only be played back in the pulse channels, WAVE and KIT instruments in the wave channel, and NOISE instruments in the noise channel.



Figure 1.4: Instrument Screen

Let's try out the sampled drum kits. Now, we have to change channel to the wave channel. Go back to the song screen, move the cursor over to the wave channel, and create a new chain and a new phrase by tapping A. Enter a note by tapping A, then SELECT+RIGHT to edit the instrument. Change the instrument type to KIT by pressing A+RIGHT on the type field, then go back to the phrase screen. Now, you should be able to enter drum sounds the same way you entered notes before.

To create new chains and phrases, move the cursor to an empty step in song or chain screen and tap A twice.

1.7 Initial Troubleshooting

Does your cartridge not start, crash, or act strange in other ways? Here are some things to try.

- Clean cartridge pins using a cotton swab and alcohol.
- Re-insert the cartridge a couple of times to remove oxide.
- Make sure that the cartridge is firmly plugged in. Sometimes it can help to put a piece of tape on the cartridge to give it a snug fit.
- Replace batteries with fresh ones.
- Do a full reset of the cartridge memory. This is done by pressing SELECT+A+B on the LOAD/SAVE FILE button in project screen.

- Certain Game Boy Advance/Nintendo DS cartridges do not work with Little Sound Dj. If you have problems with such a cartridge, try one of the Little Sound Dj builds named “Goomba”.
- Search for help on the Little Sound Dj Wiki (<http://wiki.littlesounddj.com>) or ask in the Facebook group.

1.8 Hexadecimal Number System

Before moving on to the next chapter, now is a good time to get introduced with the hexadecimal number system that Little Sound Dj uses for representing values.

The hexadecimal number system works just the same way as the traditional decimal number system. The only difference is that it’s base is 16 instead of 10. This means it consists of 16 unique symbols: the digits 0 to 9, followed by the letters A to F. For clarity, this manual will mark hexadecimal values with a dollar sign. As an example, let’s print a table of numbers – first with decimal digits, then with hexadecimal digits...

Decimal	1	2	3	4	5	6	7	8	9	10
Hexadecimal	\$1	\$2	\$3	\$4	\$5	\$6	\$7	\$8	\$9	\$A
Decimal	11	12	13	14	15	16	17	18	19	20
Hexadecimal	\$B	\$C	\$D	\$E	\$F	\$10	\$11	\$12	\$13	\$14

Note that the hexadecimal and decimal values are really equal; just the representations differ. The reason to use the hexadecimal system here is to save screen space; with hexadecimal numbers, it is possible to represent every byte value using no more than two digits. (The value range is 0 to 255 – that is, \$0 to \$FF.)

Representing negative numbers with two digits only can be a problem. In Little Sound Dj, the numbers are wrapping. That means, when subtracting one from the smallest possible number (\$0), it will jump to the highest possible value (\$FF). So \$FF can represent -1 as well as 255, depending on the situation.

If this does not make sense – please don’t worry too much – it will become clear as you spend time with the program.

Chapter 2

The Screens

Little Sound Dj has nine screens, laid out in a 5×2 screen map.

2.1 Screen Map

Project	Groove	Synth	Wave	
Song	Chain	Phrase	Instr.	Table

The song, chain and phrase screens are used for composing music. The wave, synth, instrument and table screens are used for making sounds. Project screen contains project settings, and groove screen controls sequencer timing.¹

You will likely spend most time in the bottom row, as that is where the composing is done.

2.2 Moving between Screens

Move between the screens using `SELECT+CURSOR`.

The upper and lower screen rows are controlled independently. That means, if you move left or right on one row, the position of the other row

¹There are also three hidden screens, not shown on the map: The file, word and help screens. We will get back to these later.

will stay the same. Some shortcuts exist for convenience: As an example, pressing SELECT+UP in song screen always goes to the project screen.

2.3 Starting and Stopping

When pressing START in the song screen, Little Sound Dj will always try to play all four channels. When pressing START in the other screens, Little Sound Dj will only try to play the channel that's indicated in the three-letter field at the right edge of the screen (PU1, PU2, WAV or NOI).

To start playing all four channels from some other screen than the song screen, press SELECT+START.

2.4 Song Screen

SONG	PU1	PU2	WAV	NOI	PU1
S 0	---	---	---	---	
S 1	---	---	---	---	
S 2	---	---	---	---	J 128
S 3	---	---	---	---	
S 4	---	---	---	---	1
S 5	---	---	---	---	2
S 6	---	---	---	---	W
S 7	---	---	---	---	N
S 8	---	---	---	---	
S 9	---	---	---	---	
S A	---	---	---	---	
S B	---	---	---	---	
S C	---	---	---	---	
S D	---	---	---	---	
S E	---	---	---	---	PGYW
S F	---	---	---	---	SCRIPT

Figure 2.1: Song Screen

The song screen is the highest level of the sequencer. This is where you arrange your songs.

The screen contains four columns, one for each channel. The columns contain lists of chains to be played from top to down. Different chains are used for different channels.

To insert a chain, move the cursor to an empty step and press A. If you want to add a new chain, press A twice. To edit a chain, move the cursor to the chain number and press SELECT+RIGHT. To remove a chain, press B+A.

To start or stop playing all channels in the song screen, press START. To instantly re-start all channels in the song screen, press SELECT+START.

2.7 Instrument Screen




Figure 2.4: Instrument Screen

There are five types of instruments available:

PULSE Makes pulse waves. Used in pulse channels 1 and 2.

WAVE Plays back waves synthesized using the synth screen. Used in the wave channel.

KIT Plays back samples from ROM. Used in the wave channel.

NOISE Makes filtered noise. Used in the noise channel.

SPEECH This instrument is locked to instrument number \$40, and is used for speech programming. Learn all about it in [chapter 7](#)!

You can change the instrument type by going to the type row and pressing A+CURSOR.

Remember that instruments don't automatically play in the right channel. For example, if you want to use a kit instrument to play drum samples, do the following:

1. Go to the song screen, move cursor to the wave column, and insert a new chain by tapping A twice on an empty step.
2. Edit the chain by pressing SELECT+RIGHT.
3. Insert a new phrase by tapping A twice.

4. Edit the phrase by pressing SELECT+RIGHT. Now, you have a new phrase placed in the wave channel.
5. Create a new instrument by moving the cursor to the instrument column and tapping A twice.
6. Press SELECT+RIGHT to edit the instrument.
7. Change the instrument type to KIT.
8. Go back to the phrase screen to start using your new instrument.



TIP!

- *In the instrument screen, press SELECT+B to copy instruments and SELECT+A to paste.*

2.7.1 General Instrument Parameters

These parameters are used in most instrument types.

NAME Name the instrument by pressing A. This is useful for keeping track of your instruments. The instrument name will also be shown in the border when selecting instruments in the phrase screen.

TYPE Instrument type.

LENGTH Sound length.

OUTPUT Send the sound to left/right/both/none speakers. (Use the headphone output to hear the difference!)

PITCH Controls the behavior of P, L and V commands. A+U/D switches pitch update speed: FAST updates pitch at 360 Hz; TICK updates pitch every tick; STEP is like FAST except that P does pitch change instead of pitch bend; DRUM is like FAST with logarithmic fall-off, useful for P kicks. A+L/R changes vibrato shape between downwards triangle, saw and square, and upwards triangle, saw and square.

TRANSP. When ON, the pitch may be affected by project and table transposes.

CMD/RATE Slows down C and R commands. Also affects P and V commands when PITCH is set to TICK. 0=fastest, F=slowest.

TABLE Selects a table to run when playing notes. To edit the table, press SELECT+RIGHT. To create a new table, press A,A. To clone the table, press SELECT+(B,A). Changing PLAY to STEP makes Little Sound Dj step through the table, advancing one step every time the instrument is triggered.

2.7.2 Pulse Instrument Parameters

INSTR	00	PU1
NAME		
TYPE	PULSE	
ADSR	A0----	128
WAVE		1
OUTPUT	LR	2
LENGTH	UNLIM	W
SWEEP	FF	H
PITCH	FAST	
TRANSP.	ON	
PU2 TSP.	00	
FINETUNE	0	
CMD/RATE	0	
TABLE	OFF	PGYW SCRIPT

Figure 2.5: Pulse Instrument Screen

ADSR Three amplitude control values. For each value, first digit sets amplitude, and the second digit sets the speed to rise or fall to the next amplitude. Speed 1 is fast, 7 is slow, 0 means hold. As an example, ADSR 31F7A0 creates an envelope with fast attack from amplitude 3 to F, slow decay to A, then infinite sustain, as shown in figure 2.6.

WAVE Wave type.

SWEEP Frequency sweep, useful for bass drum and percussion. The first digit changes pitch, the second changes pitch change speed. Only works on the first pulse channel.

The detune settings create interesting phase effects when the same phrase is played on both pulse channels:




Figure 2.6: Amplitude envelope example. ADSR=31F7A0.

PU2 TSP. Transpose pulse channel 2.

FINETUNE Detune pulse channel 1 downwards, channel 2 upwards.

2.7.3 Wave Instrument Parameters

The wave instrument plays back synth sounds generated in the SYNTH screen.

INSTR 01		WAV
NAME		
TYPE	WAVE	
VOLUME	3/LR	128
PITCH	FAST	1
TRANSP.	ON	2
FINETUNE	0	W
CMD/RATE	0	H
SYNTH	0	
PLAY	MANUAL	
SPEED	--	
LENGTH	-	
LOOP POS	-	
TABLE	OFF	PGYU SCPNT

Figure 2.7: Wave Instrument Screen

VOLUME Set amplitude (0=0%, 1=25%, 2=50%, 3=100%) and left/right output.

FINETUNE Detunes the sound.

SYNTH Select the synth sound to play back. To edit the synth sound being used, press SELECT+UP to go to the SYNTH screen. To use a new synth, tap A twice. To clone the synth, press SELECT+(B,A).

PLAY How to play back the synth sound: MANUAL, ONCE, LOOP, or PING-PONG. With MANUAL, only the first wave of the synth sound is played, allowing you to step through the sound manually using the F command.

SPEED Set how fast the synth sound should be played back.

LENGTH Set the length of the synth sound.

LOOP POS Set the loop point of the synth sound.

2.7.4 Kit Instrument Parameters

INSTR 01		WAV
NAME		
TYPE	KIT	
KIT 01	TR-606	J128
01	TR-606	1
		2
VOLUME	3/LR	W
PITCH	FAST/V	N
FINETUNE	00	
OFFSET	00/00	
LEN	AUT/AUT	
LOOP	OFF/OFF	
SPEED	1X	
DIST	CLIP	
TABLE	OFF	PGYW
		SCPAT

Figure 2.8: Kit Instrument Screen

KIT Choose the sample kits to use. The first kit will be used in the left note column in the phrase screen; the second kit will be used in the right note column in the phrase screen.

VOLUME Set amplitude (0=0%, 1=25%, 2=50%, 3=100%) and output (left/right/both/off).

FINETUNE Pitch shift.

OFFSET Set the start loop point. If **LOOP** is **OFF**, this value can be used for skipping the initial part of a sound.

LEN Sound length. **AUT** plays the sample to its end.

LOOP Loop control. **OFF**=don't loop, **ON**=loop sound and start playing from **OFFSET**, **ATK**=loop sample and start playing from the beginning.

SPEED Full speed or half speed.

DIST Selects what to do when the signal overshoots while mixing two kits. **CLIP** is the default: Hard clamp the signal to the allowed 0-**\$F** range. **SHAPE** and **SHAPE2** are similar to **CLIP**, but a bit softer, preserving the sounds better at the cost of not being as loud. **WRAP** can be used to add some interesting digital distortion. Pressing **A+(LEFT, LEFT)** while **CLIP** is selected will make the value jump out of range and play back sound from raw memory when the signal overshoots.



TIP!

- To replace the default sample kits, use the *lsdpatcher* program. <http://littlesounddj.com/lsd/latest/lsd-patcher/>

2.7.5 Noise Instrument Parameters

ADSR See description of pulse **ADSR** (2.7.2).

SHAPE Noise generator control. The first digit changes pitch by octave, the second digit divides the frequency. Set the second digit to 0-7 for periodic noise, 8-**\$F** for random noise. An in-depth technical explanation of the noise generator can be found in [gbsound.txt](#).

S MODE When set to **FREE**, noise changing commands can randomly² mute the sound. When set to **STABLE**, commands are limited so that sound will never be muted by accident.

²There is a 0.4% risk that the sound gets muted when a shape that ends with digit 8-F is changed so that it ends with digit 0-7.




Figure 2.9: Noise Instrument Screen

2.7.6 Speech Instrument Parameters

Read about the speech instrument in chapter 7.

2.8 Table Screen

Tables are sequences of transposes, commands and amplitude changes which can be run at any speed and applied to any channel. By setting a table in the instrument screen, the table will start every time you play the instrument. This allows you to create more interesting sounds than would be possible using the instrument screen alone.

Tables contain six columns. The first column is the envelope column, used to create custom amplitude envelopes. Next is the transpose column, used to transpose the played note by a number of semitones. The other columns are command columns like the one in the phrase screen.

The default table speed of one tick per step can be changed using the G command. To view different tables, press B+CURSOR.



TIP!

- Press SELECT+RIGHT on an A command in the phrase screen to edit that table. To jump back, press SELECT+LEFT.




Figure 2.11: Arpeggio Example

2.9 Groove Screen

Grooves control by which speed your phrases and tables are played back. When used well, grooves will make your music sound more lively.




Figure 2.12: Groove Screen

The sequencer is based on a time period called *tick*, which is controlled by song tempo. Ticks are very short: at 125 BPM, there are 50 ticks per second. Higher tempo means faster ticks, and the other way around. In the groove screen, you can control for how many ticks phrase or table steps should last. The groove in figure 2.12 would make the sequencer spend 6 ticks on every step.

You can also use grooves to create custom rhythms. The groove in figure 2.13 would make even note steps last 8 ticks, and odd note steps last




Figure 2.13: Swing Example

5 ticks, creating a swing effect. Grooves can also be used to create triplets and other complex rhythms.

Groove 0 is the default groove for all phrases, but it is possible to switch to another groove using the G command. This command also works in tables.

In the groove screen, select the groove you wish to edit by pressing B+CURSOR.



TIP!

- A+UP/DOWN changes the swing percentage, while preserving the total number of ticks – and thus, the resulting song speed – constant. (Example: Original value is $6/6 = 50\%$. Press A+UP. Now the value changes to $7/5 = 58\%$!)
- Press SELECT+UP on G commands to edit that groove.

2.10 Synth Screen

The synth screen features a soft synthesizer that generates sounds to be played back by the wave instruments. Each synth sound uses \$10 waves. Synth sound 0 uses waves \$00-\$0F, synth sound 1 uses waves \$10-\$1F, and so on. The generated synth sounds can be viewed in the wave screen (Section 2.11).

In total, there are 16 synth sounds. Choose which one to edit by pressing B+CURSOR.




Figure 2.14: Synth Screen

2.10.1 Fixed Synth Settings

SIGNAL Square, saw tooth or triangle.

FILTER Low-pass, high-pass, band-pass or all-pass.

DIST Distortion mode. CLIP truncates the wave to LIMIT, FOLD mirrors the wave around LIMIT, WRAP wraps around vertically.

PHASE Compress the waveform horizontally. It is applied after filtering with Q and CUTOFF. See figure 2.15 for examples.

2.10.2 Variable Synth Settings

These settings control the first and last wave of the sound, with a smooth in-between fade.

VOLUME Signal volume.


Q Resonance control. Boosts the signal around the cutoff frequency, to change how bright or dull the wave sounds.

CUTOFF Filter cutoff frequency.


VSHIFT Shifts the signal vertically. See figure 2.16 for examples.

LIMIT Limits the signal vertically using the DIST mode.


PHASE 0 = no phase, \$1F = maximum phase. See figure 2.15 for examples.




(a) Phase example. Original wave.



(b) NORMAL phasing. Compress horizontally, generate once.




(c) RESYNC phasing. Compress horizontally, loop.




(d) RESYN2 phasing. Loop, but don't compress.


Figure 2.15: Phase Examples



(a) Vshift example. Original wave.



(b) Vshifted signal. Vshift = 40, clip = wrap.



(c) Vshifted signal. Vshift = 80, clip = wrap.

Figure 2.16: Vshift Examples

2.11 Wave Screen

In the wave screen, you can view and edit the individual waveforms of the synth sounds. There are 16 (\$10) synth sounds, and each programs has \$10 waves. This means that synth sound 0 uses waves \$0-\$F, synth sound 1 uses waves \$10-\$1F, and so on.

To change selected values, press UP/DOWN. To flip selected values, press A+CURSOR. B+CURSOR navigates between different waves.

It is possible to modify multiple values at once, using the regular key presses:

SELECT+B Start selection.

SELECT+B,B Select the entire wave.

B Copy selection to clipboard.

UP/DOWN Move selection up/down.

A+LEFT/RIGHT Flip selection horizontally.

A+UP/DOWN Flip selection vertically.

SELECT+A Paste from clipboard.

2.12 Project Screen

```

PROJECT (EMPTY)
TEMPO 128
TRANSPOSE 00
SYNC OFF

CLONE DEEP
LOOK 92K / GRAY
KEY DELAY / REPEAT 7 / 2
PRELISTEN ON

HELP
CLEAN SONG DATA
CLEAN INSTR DATA
LOAD / SAVE SONG

WORK TIME 0: 09 269W
TOTAL 0: 0: 09 SCPT
  
```

Figure 2.17: Project Screen

The project screen (figure 2.17) contains settings that affect the entire program.

TEMPO Song tempo in BPM. It is possible to change the tempo either by pressing A+CURSOR, or by tapping the A button in pace with the desired tempo. When being a follower in sync mode, you can nudge the tempo by pressing A+LEFT/RIGHT, something which can be useful if devices have drifted out of sync.

TRANPOSE Adjust the pitch of the pulse and wave instruments by the given number of semitones.

SYNC Connects to other devices using the link port. Read all about sync settings in chapter 6!

CLONE Deep or slim chain cloning. Deep chain cloning will clone a chain's phrases, whereas slim cloning will re-use the old phrases. Read all about cloning in section 3.2!

LOOK Change the font and color set.

KEY DELAY/REPEAT Set repeat delay and repeat rate of the Game Boy buttons.

PRELISTEN Play notes and instruments while entering them.

HELP Enter help screen. The help screen contains a quick reference for button presses and a command list.

CLEAN SONG DATA Merge duplicate chains and phrases and clear unused ones.

CLEAN INSTR DATA Merge duplicate tables and clear unused instruments, tables, synths and waves.

LOAD/SAVE SONG Enter file screen.³

The project screen also has two clocks. The WORK TIME clock displays the time spent making the current song, in hours and minutes. When playing, it is replaced by the PLAY TIME clock, which shows for how long

³The file screen is only available for cartridges that have 1 Mbit SRAM or more. In case your cartridge doesn't have 1 Mbit SRAM, this button will be replaced with a RESET MEMORY button.

the song has been playing. The TOTAL clock shows how long the cartridge has been used in total, in days, hours and minutes.



TIP!

- To replace the default fonts and palettes, use the *lsdpatcher* program. <http://littlesounddj.com/lsd/latest/lsd-patcher/>

2.12.1 Total Memory Reset

Press SELECT+A+B on LOAD/SAVE FILE to erase all songs and bring back the cartridge to its default state. Generally, this is only useful if the cartridge got scrambled.

2.13 File Screen




Figure 2.18: File Screen

The file screen (figure 2.18) is entered by pressing the LOAD/SAVE FILE button in the project screen. It is used for saving the song you are working on to the storage memory. It can also be used to load songs from the storage memory to the work memory. The file screen allows you to keep up to 32 songs on one cartridge.

Note: The file screen is only available for cartridges that have 512 Mbit SRAM or more.

FILE Shows the file name of the song you are working on. The exclamation mark (!) indicates when changes have been made to a song.

LOAD Load a song. Press A, select the file to load and press A again.

SAVE Save song. Press A, select the slot to save to and enter the file name.

ERASE Erase a song. Press A, select the file to erase and press A again.

BLOCKS USED Shows how much of the storage memory that is used. One block equals 512 bytes. The digits on the bottom are hexadecimal, meaning there is a total of $\$BF * 512 = 97,792$ available bytes.

To cancel an operation in this screen, simply press B.



TIP!

- There is a useful file manager application available at <http://littlesounddj.com/lsd/latest/lsd-manager/>.

2.13.1 Song List

The song list presents song name, version number and file size. When saving, the song is compressed, so the resulting file size will vary with different songs. To start working on a new song, load from the (EMPTY) slot.



TIP!

- While in the song list, it is possible to press SELECT+A to load a song without switching to the song screen, and START to start/stop songs. In this way, you can load and play songs without jumping back and forth between screens. This can be handy if you are playing a live show with prepared tracks and want fewer things to think about.

2.14 Border Information

Various useful data is displayed in the screen border.




Figure 2.19: Border Information

1. Screen title. Shows what is being edited.
2. The channel being edited, that is, the selected song screen column.
3. Chain position being edited.
4. Current tempo in beats per minute (BPM).
5. Shows what is being played on the channels. MUTE appears when pressing B+SELECT or B+START.
6. The waveform being played on the wave channel.
7. The name of the instrument being selected in the phrase screen.
8. Sync status.
9. Screen map.

Chapter 3

Advanced Techniques

3.1 Copy and Paste

Little Sound Dj has a clipboard for temporary data storage. Pressing B+A will cut the value under the cursor and store it on the clipboard. The value can then be pasted by pressing SELECT+A.

In most screens, it is possible to mark up blocks by pressing SELECT+B and moving around the cursor. When having marked up a block, it can be copied to the clipboard by pressing B, or cut to the clipboard by pressing SELECT+A. The clipboard contents can then be pasted by pressing SELECT+A.

Some quick-mark button presses are implemented:

- SELECT+(B, B) = quick-mark a column or row.
- SELECT+(B, B, B) = quick-mark an entire screen.

When having marked a block, you can change all data inside that block by pressing A+CORSOR. This can be used, for example, to transpose several notes quickly.

3.2 Cloning

Cloning is a shortcut that can save you much unnecessary copy and paste work. It allows you to create copies of chains, phrases, instruments and tables directly from the song, chain, phrase and instrument screens.

Let's imagine you want to make a slightly altered version of the melody in chain 0. Go to the song screen, tap A on 00 to pick the number, then tap A again on a down-below empty step so that you get:

00
00

Now, move the cursor to the second 00 and press SELECT+(B, A) to make a copy of chain 0.

3.2.1 Deep vs. Slim-Cloning

There are two different cloning modes: deep and slim cloning, selectable from the project screen.

When slim-cloning a chain, a new chain appears that contains the same phrases as the original.

When deep-cloning a chain, a new chain appears with copies of the original phrases.

The advantage of deep-cloning is that you lessen the risk of modifying old phrases by accident. The drawback is that you will run out of phrases faster. Also, your songs might take up more space when saved in the file screen.

If you run out of phrases, use CLEAN SONG DATA in project screen. (Section 2.12.)

3.3 The Importance of Backups

Some words of caution from many peoples hard-earned experience: When using a Game Boy cartridge, backup your songs! Most Game Boy cartridges depend on an internal battery that will run out, losing your songs in the process. If you care about your music, do regular backups, or at least record your songs to prevent them from being lost forever.

3.4 Muting, Soloing and Panning

- Press B+SELECT in any screen to mute the channel. If the B button is released before SELECT, the channel stays muted until B is pressed again.
- Press B+START in any screen to solo the channel. If the B button is released before START, the other channels stay muted. If the START button is released first, all channels will be turned on again.
- Press B+LEFT/RIGHT in the song screen to pan a channel left or right.

3.5 Live Mode

The live mode is a special flavor of the song screen, which allows starting and stopping chains one by one. It allows different channels to play at different song positions. To toggle between song and live mode, press SELECT+LEFT in the song screen.

To play a chain, move the cursor to the chain and press START. To stop playing the chain, move the cursor to its channel and press SELECT+START. If another chain is already playing, the starts and stops are queued until the chain has been played through. Tapping START twice speeds up the switch so that it happens when the currently playing phrase ends.



TIP!

- To start or stop several chains at once, mark them before pressing START or SELECT+START. (Marking is described in section 3.1.)

3.5.1 Chain Loops

Chain loops can be a useful live mode technique. After playing the last chain, the song sequencer rewinds until it reaches an empty step, rather than going all the way to the top.

Imagine the setup in figure 3.1, and that we start playing chain 2. The player will now loop chains 2 and 3. Having a bunch of chain loops to alternate between might be useful during a live performance.

SONG	PU1	PU2	WAV	NOI	PU1
S0	S0	--	--	--	
S1	01	--	--	--	
S2	--	--	--	--	J128
S3	--	--	--	--	
S4	02	--	--	--	1
S5	03	--	--	--	2
S6	--	--	--	--	4
S7	--	--	--	--	N
S8	--	--	--	--	
S9	--	--	--	--	
SA	--	--	--	--	
SB	--	--	--	--	
SC	--	--	--	--	
SD	--	--	--	--	
SE	--	--	--	--	PGYW
SF	--	--	--	--	SCRIPT

Figure 3.1: Chain Loop Example

3.6 Synthetic Drum Instruments

Creating drum instruments without using the sampled drum kits can be very useful, as it gives greater flexibility in how to make use of the channels. Here are some starting-out ideas.

3.6.1 Pulse Bass Drum

The easiest way to create a bass drum is by using pulse channel 1. ADSR should have a strong attack and fast decay – try setting it to \$C1. WAVE is typically 50-50 high/low, even though other waves can be used for a more distorted sound. SWEEP should have high initial frequency and fast decay; try setting it to \$E3, and play the instrument at note C-6. For a snappier kick, experiment with ADSR and LENGTH parameters. Set TRANSPOSE to OFF to prevent chain transposes from changing the pitch.

3.6.2 Snare Drum

Use the noise channel for snare drum sounds. The ADSR setting should have a strong attack and fast decay – try setting it to \$D1. Use of the LENGTH parameter will make it snappier. Adjust the timbre using SHAPE – values close to \$EC might prove useful.

3.6.3 Hi-Hats and Cymbals

Use the noise channel for hi-hats and cymbals. Use a SHAPE value of \$FF for a timbre with high frequency content. Change ADSR to get the desired amplitude envelope. For cymbals, a SHAPE value near \$EE will make for a somewhat rougher timbre.

3.6.4 Taking Advantage of Tables

For adding that extra punch to snares, use the table transpose column to change the noise shape rapidly. (See figure 3.2f.)

3.6.5 Wave Bass Drum

For the best sounding bass drum, use the synthesizer in the wave channel. Set the PITCH to DRUM by pressing A+UP, and set TRANSP. to OFF. On the synth screen, choose the triangle signal, and set VOLUME to \$30. Set a table


```

INSTR 00          PU1
NAME      [BASS]
TYPE      PULSE
                J128
ADSR      C100--
WAVE      [ ] LA
OUTPUT    [ ] LA
LENGTH    UNLIM
SWEEP     E3
PITCH     FAST
TRANSP.   ON
PU2 TSP.  00
FINETUNE  00
CMD/RATE  0
TABLE     OFF
                PGYW
                SCPIT
    
```

(a) Bass Drum

```

INSTR 00          NOI
NAME      [SNARE]
TYPE      NOISE
                J128
ADSR      D100--
WAVE      [ ] LA
OUTPUT    [ ] LA
LENGTH    30
SHAPE     ED
S MODE    FREE
CMD/RATE  0
TABLE     OFF
                PGYW
                SCPIT
    
```

(b) Snare Drum

```

INSTR 00          NOI
NAME      [HH]
TYPE      NOISE
                J128
ADSR      9100--
WAVE      [ ] LA
OUTPUT    [ ] LA
LENGTH    16
SHAPE     FF
S MODE    FREE
CMD/RATE  0
TABLE     OFF
                PGYW
                SCPIT
    
```

(c) Closed Hi-Hat

```

INSTR 00          NOI
NAME      [OH]
TYPE      NOISE
                J128
ADSR      915700
WAVE      [ ] LA
OUTPUT    [ ] LA
LENGTH    UNLIM
SHAPE     FF
S MODE    FREE
CMD/RATE  0
TABLE     OFF
                PGYW
                SCPIT
    
```

(d) Open Hi-Hat

```

INSTR 00          NOI
NAME      [CYM]
TYPE      NOISE
                J128
ADSR      B16700
WAVE      [ ] LA
OUTPUT    [ ] LA
LENGTH    UNLIM
SHAPE     EE
S MODE    FREE
CMD/RATE  0
TABLE     OFF
                PGYW
                SCPIT
    
```

(e) Cymbal

```

TABLE 00          PU1
VOL  TSP CMD      CMD
0  00  F0  ---
1  00  00H00  ---
2  00  00  ---
3  00  00  ---
4  00  00  ---
5  00  00  ---
6  00  00  ---
7  00  00  ---
8  00  00  ---
9  00  00  ---
A  00  00  ---
B  00  00  ---
C  00  00  ---
D  00  00  ---
E  00  00  ---
                J295
                PGYW
                SCPIT
    
```

(f) Snare Drum Table

Figure 3.2: Synthetic Drum Instruments

```

INSTR 00                                WAV
NAME   INSTR                             J128
TYPE   WAVE
VOLUME 3/LR                               1
PITCH  DRUM/V                               2
TRANSP. OFF                               W
FINETUNE 0                                N
CMD/RATE 0
SYNTH 0
PLAY   MANUAL 0
SPEED  --
LENGTH --
LOOP POS --
TABLE PLAY 00                            PGYU
SCPTIT
    
```

(a) Bass Drum Instrument

```

SYNTH 0                                WAV
SIGNAL  WA
FILTER  LOUP                               J128
DIST    CLIP
PHASE   NORMAL
WAVE    00-0F                               1
VOLUME  30 10                               2
0        0 0                                W
CUTOFF  FF FF                               N
VSHIFT  00 00
LIMIT   F F
PHASE    00 00
PGYU
SCPTIT
    
```

(b) Bass Drum Synth

```

WAVE 00
      898DFFFFFFFFFF089
      86420000000000246
PGYU
SCPTIT
    
```

(c) Bass Drum Wave

```

TABLE 00                                WAV
VOL  TSP CMD  CMD
0  00 00PC0  ---
1  00 00L80  ---
2  00 00-   ---
3  00 00-   ---
4  00 00-   ---
5  00 00-   ---
6  00 00-   ---
7  00 00-   ---
8  00 00-   ---
9  00 00-   ---
A  00 00-   ---
B  00 00-   ---
C  00 00K00  ---
D  00 00-   ---
E  00 00-   ---
F  00 00-   ---
PGYU
SCPTIT
    
```

(d) Bass Drum Table

Figure 3.3: Wave Channel Bass Drum

for the instrument. On step 0 of the table, use a fast P command such as \$C0. On line 1, put \$80 in the TSP column and use an L command with a value such as \$30. This will transpose the bass drum to the lowest possible note without wrapping to a higher pitch. Feel free to experiment with different synth parameters or different values for the P and L commands to shape the sound of the kick, as well as playing the instrument at note C-5, C-6, or above. (See figure 3.3.)

Chapter 4

Overview of Key Presses

This is an overview of key presses valid in the phrase screen. Most will work in other screens, too.

Editing Notes

A insert note on empty step

A+RIGHT note up

A+LEFT note down

A+UP octave/+10 up

A+DOWN octave/-10 down

B+A cut note to clipboard

Marking blocks

SELECT+B start marking

SELECT+(B, B) mark row

SELECT+(B, B, B) mark all

When Having Marked a Block...

A+LEFT all marked down

A+RIGHT all marked up

A+UP all marked octave/+10 up

A+DOWN all marked octave/-10 down

Copy/Paste Action

B copy marked block to the clipboard

SELECT+A cut the marked block to the clipboard

SELECT+(B, B, B, B) copy the entire screen to the clipboard

SELECT+A paste from the clipboard

Switching Phrases

B+LEFT view the phrase in the leftmost channel

B+RIGHT view the phrase in the rightmost channel

B+UP view previous phrase in chain

B+DOWN view next phrase in chain

Start/Stop in Song Mode

START start/stop playing this phrase

SELECT+START start/stop playing all channels

Start/Stop in Live Mode

START start playing selected chain after next chain end

START, START start playing selected chain after next phrase end

SELECT+START stop playing current chain when it ends

SELECT+(START, START) stop playing current chain after next phrase end

Muting and Soloing

B+SELECT mute this channel

B+START solo this channel

Chapter 5

Commands

Commands can be used to do all sorts of things in phrases and tables. It is a good idea to skim through this chapter at least once, to get an idea of what they can do.



TIP!

- *Tapping A,A on a command shows a scrolling help text in the top of the screen. A+L/R can then be used to browse through the commands. Pause the scrolling text by holding SELECT.*

5.1 A: Table Start/Stop

Starts or stops tables in the current channel. Use the table number you want to start, or 20 for stopping.

A03 start table 3

A20 stop table

5.2 B: MayBe

5.2.1 In Phrases (MayBe Play Note)

Controls how likely it is that the note or sample(s) to the left will be played. First digit sets probability for left kit, second digit sets probability for notes and right kit.

B00 Never play note

B0F Always play note/right kit sample

BF0 Always play note/left kit sample

B08 Play note/right kit sample about 50% of the time

5.2.2 In Tables (MayBe Hop)

A hop that only happens sometimes. First digit sets probability, second digit sets destination row.

BF5 Hop to row 5, 15 times out of 16

B84 Hop to row 4, about 50% of the time

B03 Never hop to row 3

5.3 C: Chord

5.3.1 For Pulse and Wave Instruments:

Runs an arpeggio that extends the base note with the given semitones. The speed may be slowed down using `CMD/RATE` in instrument screen.

C37 plays a minor chord: 0, 3, 7, 0, 3, 7, 0, 3, 7, ...

C47 plays a major chord: 0, 4, 7, 0, 4, 7, 0, 4, 7, ...

C0C plays 0, 0, C, 0, 0, C, 0, 0, C, ...

CC0 plays 0, C, 0, C, 0, C, ...

CCC plays 0, C, C, 0, C, C, 0, C, C, ...

C00 resets chord

5.3.2 For Noise Instruments:

Applies S command with the given value every second tick.

5.4 D: Delay

Delay the triggering of a note with the given number of ticks.

5.5 E: Amplitude Envelope

5.5.1 For Pulse and Noise Instruments

The first value digit sets the initial amplitude (0=min, \$F=max); the second digit sets the release (0,8: no change, 1-7: decrease, 9-\$F: increase).

5.5.2 For Wave Instruments

E00 volume 0%

E01 volume 25%

E02 volume 50%

E03 volume 100%

5.6 F: Wave Frame/Finetune

5.6.1 For Pulse Instruments:

The first digit sets PU2 TSP., the second FINETUNE. See section [2.7.2](#).

5.6.2 For Kit Instruments:

Modifies the sample position. \$00-\$7F steps forward, \$80-\$FF steps back.

5.6.3 For Wave Instruments:

Change the wave frame being played on the wave channel. This command is relative, meaning that the value is added to the current frame number. It can be used for playing through synth sounds manually.



TIP!

- *Since a synth sound contains 16 (\$10) waves, issuing the command F10 jumps to the next synth sound.*

Example:

F01 If wave frame 3 is being played, advance 1 frame and start playing frame number 4.

5.7 G: Groove Select

Select the groove to use when playing phrases or tables.

Example:

G04 select groove 4

5.8 H: Hop

H hops to a new play position. It can also be used to stop playing.

5.8.1 H in Phrases

H00-H0F Hop to next phrase. The digit sets destination phrase step.

H10-HFE Hop back within the phrase. The first digit sets number of times to hop back, the second digit sets destination step.

HFF Stop playing song (or channel, if in live mode).



TIP!

- *To compose in waltz time (3/4), put H00 commands on step C in every phrase.*

5.8.2 H in Tables

In the table screen, H is used for creating table loops. The first digit sets how many times the hop should be done before moving on; 0 means “forever.” The second digit sets the table step to jump to. Loops can be nested; that is, you can have smaller loops inside bigger ones.

Example:

H21 hop twice to table position 1.

H04 hop to table position 4 forever.

5.9 K: Kill Note

K instantly stops the sound, causing an audible click. If the click is not desired, better options might be E00 for wave channel and E11 for pulse and noise channels.

Example:

K00 kill note instantly

K03 kill note after 3 ticks

5.10 L: Slide

Slides to the target note in the given duration. If the instrument’s PITCH setting is TICK, the duration is given in ticks, otherwise in n/360 seconds.

Example:

```
C-4 ---
F-4 L40
--- ---
C-4 L10
```

This will result in a slide that starts with C-4, bends to F-4, and then quickly bends back to C-4.

	VOL	TSP	CMD	CMD	PU1
TABLE	00				
0	00	0C	---	000	
1	00	F4	L80	---	
2	00	0C	---	---	J295
3	00	00	A20	---	
4	00	00	---	---	1
5	00	00	---	---	2
6	00	00	---	---	W
7	00	00	---	---	
8	00	00	---	---	
9	00	00	---	---	
A	00	00	---	---	
B	00	00	---	---	
C	00	00	---	---	
D	00	00	---	---	
E	00	00	---	---	
F	00	00	---	---	
					PGYW
					SCPIn

Figure 5.1: Table Slide

5.10.1 L in Tables

The L command may be used in the left table command column. The transpose column will then set target note relative to the base note.

Transposes and slides are added together independently. In the above example, step 0 transposes one octave up. In step 1, the L command starts sliding one octave down while keeping the transpose from step 0 unchanged. In step 2, the L command is allowed to continue while the transpose stays one octave up. After some time, L will stop one octave down, canceling out the transpose and returning to the base note.

5.11 M: Master Volume

Changes the master output volume. The first digit modifies the left output, the second digit the right. The volume can either be set with an absolute value, or changed by a relative value.

Values 0-7 are used to specify absolute volumes. Values 8-\$F give the volume a relative change; 8 is no change, 9-\$B increase, \$D-\$F decrease.

Examples:

M77 maximize volume

M08 minimize left volume, leave right volume unchanged

M99 increase volume with 1 step

MFE decrease left volume with 1 step, right volume with 2 steps

5.12 O: Set Output

Pan channel to left, right, none or both outputs.

5.13 P: Pitch Bend

5.13.1 For Pulse, Wave and Kit Instruments:

Does a pitch change with the given speed. The behavior depends on the instrument's PITCH setting:

DRUM Logarithmic pitch bend that updates at 360 Hz.

FAST Linear pitch bend that updates at 360 Hz.

TICK Pitch bend that updates every tick.

STEP Immediate pitch change without bend.

Example:

P02 Pitch change up with speed 2.

PFE Pitch change down with speed 2. (\$FE=-2)

5.13.2 For Noise Instruments:

Applies S command with the given value every tick.

5.14 R: Retrig/Resync

Retrig plays the latest played note again. The first digit modulates the volume (0=no change, 1-7=increase, 9-\$F=decrease). The second digit sets retrigger rate, 0 being the fastest and \$E the slowest, and \$F meaning only retrigger once.

R8x means resync: With this option, the sound generator restarts at a very high rate. The pulse channels have a special quirk which makes resync slow down the sound, allowing it to go half an octave deeper.

Example:

R00 retrigger the sound every tick

R0F retrigger once

R80 restart the sound generator at 360 Hz

RF3 retrigger the sound every fourth tick, decreasing amplitude (echo effect)

5.15 S: Sweep/Shape

This command has different effects for different instrument types.

5.15.1 Pulse Instruments

Frequency sweep, useful for bass drums and percussion. The first digit changes pitch, the second changes pitch change speed. Only works on the first pulse channel.

5.15.2 Kit Instruments

S changes the loop points. The first digit modulates the offset value; the second digit modulates the loop length. (1-7=increase, 9-\$F=decrease.) Used creatively, this command can be very useful for creating a wide range of percussive and timbral effects.

5.15.3 Noise Instruments

Alters noise shape (see section 2.7.5). The command is relative, meaning that the digits are independently added to the active noise shape.

5.16 T: Tempo

Changes the tick rate to match the given beats per minute (BPM) value. The BPM is accurate only if the active groove has 6 ticks per note step. If the groove has some other number of ticks per note step, the BPM value should be adjusted according to the formula $lsdj_bpm = (desired_bpm \times ticks_per_step) / 6$. T28-TFF selects 40-255 BPM, T00-T27 selects 256-295 BPM.

Example:

T80 set tempo to 128 BPM

TFF set tempo to 255 BPM

T27 set tempo to 295 BPM

5.17 V: Vibrato

Adds vibrato. Not available for noise instruments. The vibrato speed and shape depends on the instrument's PITCH setting. The first digit sets speed, second sets depth.

Depth	0	1	2	3	4	5	6	7
Semitones	0.125	0.25	0.375	0.5	0.75	1	1.5	2
Depth	8	9	A	B	C	D	E	F
Semitones	2.5	3	3.5	4	5	6	7	8

Example:

V42 speed=4, depth=0.375 semitones

V00 reset vibrato

5.18 W: Wave

5.18.1 For Pulse Instruments:

Changes waveform.

5.18.2 For Wave Instruments:

The first digit sets synth sound speed, the second sets synth sound length. 0 = no change. The synth restarts if length is changed.

5.19 Z: RandomiZe

The Z command repeats the last command that is not Z or H, adding a random number to the original command value. The Z value controls the maximum value of each digit to be added.

Example:

Z02 adds one of 0, 1, 2 to the original value.

Z20 adds one of 0, 10, 20 to the original value.

Z22 adds one of 0, 1, 2, 10, 11, 12, 20, 21, 22 to the original value.

Chapter 6

Synchronization

LSDj can synchronize with other devices through the link port, so that it is possible to run both in exactly the same tempo. Enable synchronization by changing the SYNC mode in the project screen.

IMPORTANT: When running synchronized, use a groove based on 6 ticks/step. Otherwise, the resulting speed might be wrong.

6.1 Game Boy to Game Boy Sync

It is possible to sync two Game Boys running LSDj using a Nintendo Game Link cable.

6.1.1 Activating LSDj Sync

Make sure that both Game Boys are turned off. Connect the Game Boys using the link cable. Now, turn on the Game Boys, and go to the project screens. Set the SYNC mode to LSDJ on both Game Boys.

6.1.2 Song Play

When in song mode, pressing START starts both Game Boys from the same song position. The Game Boy on which you pressed START is the one that sends sync signals; this is indicated by the text LEAD appearing in the right margin. The other Game Boy shows the text SYNC, indicating that it is receiving sync signals.

6.1.3 Live Play

Pressing **START** in live mode makes the Game Boy start like usual; also **LEAD/SYNC** texts indicate that sync signals are sent between the Game Boys. When pressing **START** on the following Game Boy, the text **WAIT** appears while it is waiting for a phrase start.

6.1.4 Clipboard Transfer

When two Game Boys are linked and not playing, copying groove, chain, phrase, instr, table or synth data on one Game Boy will transfer the copied data so it can be pasted on the other Game Boy.

6.1.5 Switching Lead while Playing

In some cases, it can be useful to switch which Game Boy is the lead while playing. Do this by following steps:

1. Set Game Boys to LSDJ sync.
2. Start playing.
3. Set the following Game Boy to sync OFF.
4. Stop lead Game Boy.
5. Set the following Game Boy to sync LSDJ. It now becomes the lead.

6.2 MIDI Sync

MIDI sync requires a special MIDI sync cable for Game Boy. For information on how to build a MIDI to Game Boy adapter, please refer to the website at <http://www.littlesounddj.com>.

Usage: Plug in the sync device before turning on your Game Boy. Then, set LSDj to MIDI sync mode. Pressing **START** will now make LSDj wait for and sync with any incoming MIDI clock signals. LSDj should use grooves based on 6 ticks.




TIP!

- When LSDj is following, it is possible to temporarily play slower or faster by pressing A+LEFT / RIGHT on tempo in project screen. This can be very useful when being hooked up to some external hardware that has drifted slightly out of sync.

6.3 Analog In

LSDj can sync to music equipment that sends analog sync signals. This sync mode has been tested with the Korg Volca series, but works with other gear too; you can find a list at http://littlesounddj.wikia.com/wiki/Analog_Sync_Compatibility.

A cable should be easy to make, since no particular electronics are needed: all it takes is to splice a Nintendo Game Link Cable and a 3.5 mm mini plug cable together. The wires should be connected as shown in the below diagram: GND goes to GND, CLK goes to CLK.




As a clarification, the above diagram is looking at the cable, and the wires are probably not red and blue in reality.

Once the cable is built, connect it to the Game Boy serial port and the SYNC OUT of your synthesizer. In project screen, set LSDj to ANALOG sync mode. The TICKS/STEP setting controls how many LSDj ticks should be generated for each incoming sync signal. Depending on the synthesizer, it may be necessary to change this setting to make LSDj run at the right speed. For Korg Monotribe, it should typically be set to 6, whereas for Korg Volca, it should be C.

6.4 Analog Out

Analog Out works similar to Analog In, except that in this mode, LSDj is responsible for sending the sync signal. The cable is different from the one

used for Analog In. Build it by connecting the wires as follows:



As a clarification, the above diagram is looking at the cable, and the wires are probably not red and blue in reality. This cable should be connected to SYNC IN of your synthesizer.

6.5 Troubleshooting Cables

When making cables, double and triple check that the wires are connected to the right pins. You will need a multimeter for probing the pins. If they are not connected exactly like they should, you can get cables that nearly work, but the sync is a little off. The most common problem is flipped pins; remember that the diagrams are looking at the cable, not from it!

6.6 Keyboard Control

The KEYBD sync mode allows connecting a PS/2 keyboard to the Game Boy and playing it like a piano. This can be fun for live shows and improvisation. For information on how to build a PS/2 keyboard to Game Boy adapter, please refer to the Wiki site: <http://wiki.littlesounddj.com>

The keyboard must be calibrated once is plugged in. To do this, go to the project screen, set sync mode to KEYBD, and press A on the PS/2 DELAY setting. Then, press the down arrow key on your PS/2 keyboard repeatedly until LSDj says OK!

To get sound when playing the keyboard, first go to phrase screen and move cursor to note column, or press START to play the keyboard while the song is running.

6.6.1 Keyboard Note Layout

SPACE play using custom table

F1/F2 octave down/up




Figure 6.1: PC Keyboard Map

F3/F4 instrument down/up

F5/F6 select custom table to assign to SPACE

F8 change pulse instrument playback channels (PU1, PU2, PU1+2)

F9-F12 toggle channel mute (switches on key press)

CTRL+(F9-F12) tap channel mute (switches on key press and release)

CURSOR MOVEMENT KEYS move around cursor

ENTER play chain

CTRL+ENTER stop chain

PAGE UP/DOWN B+UP/DOWN

Chapter 7

Speech Programming

7.1 Introduction

Little Sound Dj has 59 speech sounds, called allophones. By combining these sounds, it is possible to create any English word or phrase.

The speech instrument is locked to instrument number \$40 and can only be used in the wave channel. It contains 42 words, mapped out from note C-2 to note F-5.

INSTR 40			PU1
TYPE	SPEECH		
C#2	D 3	E 4	J 128
D#2	D#3	F 4	
D#2	F 3	F#4	1
E#2	F#3	G 4	2
F#2	G 3	A 4	W
F#2	G#3	A#4	
G#2	A 3	B 4	
G#2	A#3	C#5	
A#2	B 3	C#5	
A#2	C 4	D#5	
B#2	C#4	D#5	
C#3	D 4	E 5	P G Y W
C#3	D#4	F 5	S C P M W

Figure 7.1: Speech Instrument Screen

To edit a word, press SELECT+RIGHT to get to the word screen. The left column contains the allophones to be played, the right column sets their duration. The word in figure 7.2 is supposed to say "Little Sound Dj."

To make the words easy to remember, rename them by tapping A in the speech instrument screen.

WORD	C	2	PU1
PHN	LEN		
0	02		
1	06		
2	03		J128
3	08		
4	04		1
5	08		2
6	05		W
7	03		H
8	03		
9	08		
A	05		
B	08		
C	08		
D	08		
E	08		
F	08		
G	08		
H	08		
I	08		
J	08		
K	08		
L	08		
M	08		
N	08		
O	08		
P	08		
Q	08		
R	08		
S	08		
T	08		
U	08		
V	08		
W	08		
X	08		
Y	08		
Z	08		
[08		
]	08		
{	08		
}	08		
~	08		
PGYW			
SCRIPT			

Figure 7.2: Example Word

7.2 Allophones

- When selecting allophones, care about how they sound, not how they are spelled.
- A sound may be different depending on its position within a word. For example, the K in “coop” will sound different from the K’s in “keep” and “speak”.

Allophones marked with * loop indefinitely.

7.2.1 Short vowels

*IH sitting, stranded

*EH extent, gentlemen

*AE extract, acting

*UH cookie, full

*AD talking, song

*AX lapel, instruct

7.2.2 Long vowels

IY treat, people, penny

EY great, statement, tray

AY kite, sky, mighty

OI noise, toy, voice

UW1 after clusters with YY: computer

UW2 in monosyllabic words: two, food

OW zone, close, snow

AW sound, mouse, down

EL little, angle, gentlemen

7.2.3 R-colored vowels

ER1 letter, furniture, interrupt

ER2 monosyllables: bird, fern, burn

OR fortune, adorn, store

AR farm, alarm, garment

YR hear, earring, irresponsible

XR hair, declare, stare

7.2.4 Resonants

WW we, warrant, linguist

RR1 initial position: read, write, x-ray

RR2 initial clusters: brown, crane, grease

LL like, hello, steel

YY1 clusters: cute, beauty, computer

YY2 initial position: yes, yarn, yo-yo

7.2.5 Voiced fricatives

VV vest, prove, even

DH1 word-initial position: this, then, they

DH2 word-final and between vowels: bathe, bathing

ZZ zoo, phase

ZH beige, pleasure

7.2.6 Voiceless fricatives

***FF** fire, fox

***TH** this, they

***SS** sit, smile

SH shirt, leash, nation

HH1 before front vowels: YR, IY, IH, EY, EH, XR, AE

HH2 before back vowels: UW, UH, OW, OY, AO, OR, AR

WH white, whim, twenty

7.2.7 Voiced stops

BB1 final position: rib; between vowels: fibber, in clusters: bleed, brown

BB2 initial position before a vowel: beast

DD1 final position: played, end

DD2 initial position: down; clusters: drain

GG1 before high front vowels: YR, IY, IH, EY, EH, XR

GG2 before high back vowels: UW, UH, OW, OY, AX; and clusters: green, glue

GG3 before low vowels: AE, AW, AY, AR, AA, AO, OR, ER; and medial clusters: anger; and final position: peg

7.2.8 Voiceless stops

PP pleasure, ample, trip

TT1 final clusters before SS: tests, its

TT2 all other positions: test, street

KK1 before front vowels: YR, IY, IH, EY, EH, XR, AY, AE, ER, AX; initial clusters: cute, clown, scream

KK2 final position: speak; final clusters: task

KK3 before back vowels: UW, UH, OW, OY, OR, AR, AO; initial clusters: crane, quick, clown, scream

7.2.9 Affricates

CH church, feature

JH judge, injure

7.2.10 Nasal



MM milk, alarm, example




NN1 before front and central vowels: YR, IY, IH, EY, EH, XR, AE, ER, AX, AW, AY, UW; final clusters: earn




NN2 before back vowels: UH, OW, OY, OR, AR, AA




Chapter 8




The Sample Kits



Machine	Year	Info
SP0256-AL2 General Instruments	1981	 <p>The SP0256-AL2 Speech Processor IC contains a programmable digital filter that can be made to model a vocal tract. The 16k ROM stores both data and instructions. The pulse width modulated output can produce speech with a frequency range of 5kHz and a dynamic range of 42 dB.</p>
TR-606 Roland	1981	 <p>The Roland TR-606 Drumatix is a programmable analogue drum machine. It was designed to couple with the TB-303 Bassline. The TR-606 has a very original sound and remains popular today.</p>

Machine	Year	Info
TR-707 Roland	1984	 <p data-bbox="655 712 1353 860">The Roland TR-707 has the same functions as the TR-909 with all PCM sounds. Starting with this model, Roland began using an LCD display to show the rhythm matrix and tempo.</p>
TR-727 Roland	1985	 <p data-bbox="655 1205 1353 1352">The Roland TR-727 is identical to the TR-707, with the exception that its sounds are Ethnic/Latin percussion. It is meant to complement a rhythm section, rather than be a main unit.</p>
TR-808 Roland	1980	 <p data-bbox="655 1736 1353 1883">The Roland TR-808 has played a defining role for the 80's Hip Hop and Electro movement. It is still highly popular, thanks to its unmistakably original sounds.</p>

Machine	Year	Info
TR-909 Roland	1983	 <p data-bbox="544 667 1241 853">The Roland TR-909 is one of the most popular drum machines ever. It has PCM sounds for cymbal and hi-hat, but all other instruments still come from analogue circuitry. The sounds are very useful for House and Techno music.</p>
CR-78 Roland	1978	 <p data-bbox="544 1173 1241 1323">The Roland CR-78 is perhaps the most luxurious rhythm machine ever made. The guiro and tambourine are still unique as of today, and bass, snare and bongos sound very soft and rich.</p>
CR-8000 Roland	1981	 <p data-bbox="544 1711 1241 1859">The Roland CR-8000 was introduced after the TR-808 – it has the same analog engine. The hi-hat sounds more realistic than older rhythm machines, but the hand clap sounds like an electric snare.</p>

Machine	Year	Info
DR-55 Boss	1979	 <p>The Boss Dr. Rhythm range of drum machines is especially designed for guitar players who need a mobile drummer. The DR-55 is a simple analogue drum machine with a very rough and direct sound.</p>
DR-110 Boss	1983	 <p>The DR-110, the successor of the DR-55, has analogue sound but is programmed digitally using a LCD rhythm matrix. It quite possibly has the best analogue handclap ever.</p>
LinnDrum	1982	 <p>The LinnDrum originally sold for \$3,000 and about 5,000 units were produced. It provided the rhythm tracks of many 1980's hit records.</p>

Machine	Year	Info
Rhythm Ace	1973	 <p data-bbox="568 689 1264 875">Ace Tone was the first company to produce electric rhythm boxes in Japan. In the UK, Bentley Pianos (who put stickers on all their products) distributed Ace Tone, and thus the machine is also known as the Bentley Rhythm Ace.</p>
Tom Sequential Circuits	1984	 <p data-bbox="568 1196 1264 1346">The sounds are a bit dirty and harsh sounding, especially next to its older brother Drumtraks, but that also gives Tom its character. The snare sounds like nothing else on this planet - it's electric!</p>
Acieed House	1990's	 <p data-bbox="568 1637 1264 1742">This set of vocal samples was derived from a bunch of popular Acid House tracks. Can you dig it?</p>

Machine	Year	Info
Ghetto Bass	1990's	
Animals Bud Melvin	2004	

A bunch of samples derived from classic Detroit/Chicago ghetto house tracks.

The winner of the 2004 Animal Sample Compo. A great selection of domestic animals.

Appendix A

SRAM Memory Map

A.1 Bank 0

A000-AFEF phrase notes

AFF0-B02F bookmarks

B030-B08F empty

B090-B28F grooves

B290-B68F song chains

B690-B88F table envelopes

B890-BDCF speech instrument words (20×42)

BDD0-BE77 speech instrument wordnames

BE78-BE79 mem initialized flag (set to "rb" on init)

BE7A-BFB9 instrument names

A.2 Bank 1

A000-A01F empty

A020-A03F table allocation table

A040-A07F instr alloc table

A080-A87F chain phrases

A880-B07F chain transposes
B080-B47F instrument parameters
B480-B67F table transposes
B680-B87F table commands, left column
B880-BA7F table command values, left column
BA80-BC7F table commands, right column
BC80-BE7F table command values, right column
BE80-BE81 mem initialized flag (set to "rb" on init)
BE82-BEA1 phrase allocation table
BEA2-BEB1 chain allocation table
BEB2-BFB1 softsynth params
BFB2-BFB2 clock, hours
BFB3-BFB3 clock, minutes
BFB4-BFB4 tempo
BFB5-BFB5 tune setting
BFB6-BFB6 total clock, days
BFB7-BFB7 total clock, hours
BFB8-BFB8 total clock, minutes
BFB9-BFB9 total clock
BFBA-BFBA key delay
BFBB-BFBB key repeat
BFBC-BFBC font (for cgb)
BFBD-BFBD sync mode (off/lsdj/midi/...)
BFBE-BFBE colorset
BFBF-BFBF sync parameter (e.g. analog in ticks/step)

BFC0-BFC0 clone (0=deep, 1=slim)

BFC1-BFC1 file changed?

BFC2-BFC2 power save

BFC3-BFC3 prelisten

BFC4-BFC5 synths locked?

BFC6-BFC9 last used instrument/channel

A.3 Bank 2

A000-AFEF phrase commands

AFF0-BFDF phrase command values

A.4 Bank 3

A000-AFFF waves

B000-BFEF phrase instruments

BFF0-BFF1 mem initialized flag (set to "rb" on init)

BFF2-BFFE empty

BFFF-BFFF version byte